

Configure SSH on Windows 10

Up

Posted by Frank

Tags:

Windows 10 Fall Creators Update comes with a hidden gem - ssh client and a less important ssh server, both based on OpenSSH. This is big news as you can now access your favorite server right from the command line without the need for PuTTY or other ssh clients.

This new feature is not installed by default so you will have to go through a few steps to make it available. This is done by following these simple steps:

1. Opening Settings
2. Click on Apps
3. Click on Manage optional features
4. Click on Add a feature
5. Scroll to OpenSSH Client (Beta) and click on it and then click the install button
6. I also had to reboot the computer but that might not be necessary

That's it not you have ssh available on the command line. Typing ssh on the command line looks like this:

ssh on the command line

If you connect to hosts using userid and password you should be ready to start using the feature. I would recommend using keys to connect, especially if you are in control over the host and can configure the ssh server to disallow PasswordAuthentication by setting "PasswordAuthentication no" in /etc/ssh/sshd_config and restarting the sshd server. Make sure you have tested that you can connect with key before you make this change.

In order to use ssh keys you will have to generate a private and a public key. If you have done this before you are most likely used to the following command:

```
ssh-keygen -t rsa -b 4096
```

That will generate a pair of RSA keys typically named id_rsa and id_rsa.pub.

The Windows 10 implementation does not look like it supports RSA keys as the above command returns the error "unknown key type rsa". Changing the command to

```
ssh-keygen -t ed25519 -b 4096
```

Does work and it does generate a pair of keys named `id_ed25519` and `id_ed25519.pub`. These will be placed in a folder called `.ssh` in the users home directory. I have not tested if it works if the `.ssh` directory is missing. I had one already from my PuTTY installation.

The next step is to log into the ssh server where you want to use the keys for authentication. When you are logged on to the server you can edit the file `~/.ssh/authorized_keys` and add a line where you past the content of `id_ed25519.pub`. Make sure it is the public file you are copying.

Logout from the server and type

```
ssh <user>@<hostname>
```

If the ssh server supports the `ed25519` format you should be able to login without using a password. When I tried this on my CentOS 7 based hosts I received errors related to the servers lack of support for the format. It was an easy fix to change that. On CentOS 7 the ssh client and server configuration files are placed in `/etc/ssh`. In the file called `sshd_config` there are by default two lines used to define the `HostKey` values in use for the server. This looks like this:

```
sshd config
```

The file `ssh_host_key_ed25519_key` is already installed in the folder. WHEN you have edited the file you must restart the `sshd` server with the command:

```
systemctl restart sshd
```

That's it, you now have access to ssh on the command line and you can connect to the server without using PuTTY or other ssh clients.

Best of all the **scp** command is also available. You can copy files to and from the server with commands like this:

```
scp <local file> <user>@<hostnam>:
```

It is important to remember the trailing `:` and any directory and filename you would like for the file on the host.

Link to this Post

[Get Next 2](#)

[Get RSS feed](#)

Recent Blog Posts

Blog Archives

Tags

[PHP {2}](#)

[C/C++ {0}](#)

Calendar

April 2026						
Su	Mo	Tu	We	Th	Fr	Sa
			1	2	3	
		4				
5	6	7	8	9	10	
		11				
12	13	14	15	16	17	
		18				
19	20	21	22	23	24	
		25				
26	27	28	29	30		